

How to Install & Run AutoCAD .dvb Macros in BricsCAD

© Mark Adams 2026
www.engineeringsurveyor.com

Note:

This example was tested on BricsCAD trial version V23 en_US_64bit
Example uses macro: VectorDevs2011.dvb and icon bitmap VectorDevs2011.bmp

Loading the Macros

1. Download, Unzip and Create folder of Macros (and bitmaps)
2. Save the Folder to eg Program Files/Bricsys/Bricscad v.../Macros
3. Open Bricscad (with VBA installed)
- 4a. Type APPLOAD (Click on "+" and navigate to macros folder to select required macros)
- 4b. Ensure AutoLoad is ticked to load macros each time BricsCAD starts. May need to restart BricsCAD to load macros.
- 4c. Type APPLOAD again to see that macro is "Loaded".

How to Run

Option 1: Run from Command line

1. Type VBARUN & Select macro from list

Option 2: Create an Icon/Menu

A. Create a Macro Shortcut

1. Type CUI
2. In the MENU Tab, in the RIGHT window, Right click BRICSCAD, Append Toolbox, eg Macros
3. Right Click "Macros" Toolbox, Append Tool

Example:

Title: VectorDevs (can be anything)

Help: (leave blank)

Command: -vbarun VectorDevs2011 (-vbarun followed by exact name of macro, WITHOUT .dwb)

Image: Click on 3 dots, Select Bitmap File, click on 3 dots, navigate to BMP file in the macros folder, OK, OK

Repeat step 3 for any more macros

B. Create a new Menu

4. Type CUI (if not already)
5. Select TOOLBAR tab
6. In the LEFT window, right-click BRICSCAD, Append Toolbar, eg Macros
7. Select VectorDevs from RIGHT hand window and DRAG into new Macro Toolbar

You should now have a Toolbar with at least one macro!

© Mark Adams 2026
www.engineersurveyor.com